

MX900030A

Connector Master

Release Note

Version 1.05

Thank you for choosing the Anritsu MX900030A Connector Master.

This release note explains the functions updated by firmware version 1.05 for the Connector Master.
It also provides notes on known software issues and usage precautions.

Contents

Item	Description
1. Release Software and Manuals ...P3	Lists software and manuals included in this upgrade
2. New Features ...P3	List new functions
3. Resolved Software Issues ...P5	Lists improvements provided by version 1.04 upgrade
4. Known Problems ...P5	Lists known problems
5. Cautions ...P5	Lists cautions for use of MX900030A
6. Upgrade Precautions ...P6	Provides important information about upgrading to version 1.05

1. Release Software and Manuals

This upgrade contains the following MX900030A software and manuals.

Download File Name	Version
MX900030A Software Version	1.05
Operation Manual	Edition
MX900030A Operation Manual	6.0

2. New Features

Function added and changed by upgrading the firmware version from 1.04 to 1.05.

- Supported G0306C.
- Supported Windows 10.

Function added and changed by upgrading the firmware version from 1.03 to 1.04.

- None.

Function added and changed by upgrading the firmware version from 1.02 to 1.03.

- None.

Function added and changed by upgrading the firmware version from 1.01 to 1.02.

- Supported G0306B. G0306B can be used 60 degrees tip.

Function added and changed by upgrading the firmware version from 1.00 to 1.01.

- Multiple VIPI files in the selected folder can be output in one report collectively.
Click Process -> Generate Report (Folder) on the menu bar to display the folder selection window. When select a folder in which multiple VIPI files are stored, all the files are output in one PDF file.
- VIPI file can be loaded by drag & drop onto the file list.
- Authorization of administrator is no longer required for starting up the MX900030A.
- Installation destination of the MX900030A is changed to "C:\Program Files\Anritsu\MX900030A".
- Saving destination (editable) of captured files is changed to the folder below.
(Files are not automatically saved in default setting.)

If your OS is Windows 7:

C:\Users\user name\Documents\Anritsu\MX900030A

If your OS is Windows XP:

C:\Documents and Settings\user name\My Documents\Anritsu\MX900030A

3. Solved Software Issues

Model Name	Description
MX900030A (V1.05)	➤ None.
MX900030A (V1.04)	➤ Fixed a bug that the Office 2013 could not be launched when the Connector Master was installed.
MX900030A (V1.03)	➤ Fixed a bug that the Connector Master crashes when executing analysis.
MX900030A (V1.02)	➤ None.
MX900030A (V1.01)	➤ None.

4. Known Problems

Software version 1.04 for the MX900030A contains the following known problems:

Model Name	Description
MX900030A	➤ None

5. Cautions

Read the following terms and conditions carefully before using the MU909014A/A1/B/B1/15B/B1.

Model Name	Description
MX900030A	➤ Make sure to start up Connector Master after connecting Fiber Scope to PC.

6. Upgrade Precautions

Download the newest firmware from the following URL.

➤ <https://www.anritsu.com/en-us/test-measurement/support/downloads?model=MU909014A1>

- Connector Master is an installer format since version 1.05. Please refer to the MX900030A Operation Manual for the installation procedure.
- Do not turn off the PC while installing the software.

If the software update fails and the MX900030A cannot restart, please contact our Anritsu sales representative.